



License Server 4.1 Release Notes

This document provides information on new and enhanced features that have been introduced into the License Server since version 4.0. It also contains a section on resolved issues that may be important to you.

Asia Pacific/Australia:
Phone: +61 2 9437 6255
pbsoftware.australia@pb.com
pbsoftware.singapore@pb.com
www.pitneybowes.com.au/software

Canada:
Phone: 1 800 268 3282
pbsoftware.canada.sales@pb.com
www.pb.com/software

Europe/United Kingdom:
Phone: +44 (0) 1491 416 600
pbsoftware.emea@pb.com
www.pitneybowes.co.uk/software

India:
Phone: +91 120 402 6000
contactindia@pb.com
www.pitneybowes.co.in/software

United States:
Phone: 1 800 327 8627
pbsoftware.sales@pb.com
www.pb.com/software

© 2013 Pitney Bowes Software Inc. All rights reserved. Pitney Bowes Software Inc. is a wholly-owned subsidiary of Pitney Bowes Inc. Pitney Bowes, the Corporate logo, MapInfo, Group 1 Software, and MapInfo Professional are [registered] trademarks of Pitney Bowes Inc. or a subsidiary. All other trademarks are the property of their respective owners.

July 22, 2013

Contents:

- **System Requirements**1
- **Installation**1
- **Progress and Resolution of Outstanding Issues**3

System Requirements

This product is tested on the following Microsoft Windows Desktop Operating Systems:

- Windows XP Professional 32-bit Service Pack 3 (SP3)
- Windows 7 Ultimate 32-bit SP1
- Windows 7 Ultimate 64-bit SP1 with 32-bit compatibility mode
- Windows 2008 Server 32-bit SP2
- Windows 2008 Server R2 64-bit SP1 with XenApp 6.0
- Windows 2008 Server R2 64-bit SP1
- Windows 8 64-bit
- Windows 2012 Server 64-bit

Installation

This section explains how to install the License Server for the following scenarios:

- **New Installation** – You are installing the License Server for the first time, or you have removed your earlier installation.
- **Upgrading Your Installation** – You are installing the License Server over an earlier version of the product.

New Installation

To install the License Server:

1. Insert the media into the drive. Right-click the `MILS_Setup.exe` file and select **Run as administrator** from the popup menu to install using elevated privileges. If a prompt for permission displays, then click **Allow** or **Yes** to proceed (if you do not respond and the message times-out, the install is unsuccessful).

On **Windows XP**, double-click the `MILS_Setup.exe` file to start the installation process.

The wizard begins to lead you through the installation process.

2. At the **Welcome** dialog box, click **Next**.
3. At the **License Agreement** dialog box, click the **I accept the terms of the license agreement** button. To print the license agreement, click **Print**. Click **Next** to proceed.
4. At the **Destination Folder** dialog box, select the location of the License Server.

The default location is `C:\Program Files\MapInfo\License Server\`

Click **Change** to select a different location.

Click **Next** when your destination folder is set.

5. At the **License Server Name and Port** dialog box, type the name of the license server in the **License Server Name** field.
6. Type the port number you want to use for the server in the **License Server Port Number** field. The default port is 27000. Click **Next**.

Note: Valid port numbers range from 1 to 65535.

7. At the **Ready to Install the Program** dialog box, click **Install**.
The License Server and License Server Utility will be installed using the settings you specified in the previous steps.
8. At the **Install Wizard Completed** dialog box, click **Finish**.

The License Server is installed.

Upgrade Installation

If you have an earlier version of the License Server installed, perform an upgrade installation.

When upgrading, you may have a short period of downtime if users attempt to access the License Server while the update is in progress. If licenses are already activated on your existing License Server, upgrading will not transfer the licenses back to Pitney Bowes Software. If you wish to transfer the licenses back to Pitney Bowes Software, please refer to *Transferring a License* in the License Server User Guide.

To install the License Server:

1. Insert the media into the drive. Right-click the `MILS_Setup.exe` file and select **Run as administrator** from the popup menu to install using elevated privileges. If a prompt for permission displays, then click **Allow** or **Yes** to proceed (if you do not respond and the message times-out, the install is unsuccessful).

On **Windows XP**, double-click the `MILS_Setup.exe` file to start the installation process.

The wizard begins to lead you through the installation process.

2. At the **Welcome** dialog box, click **Next**.
3. At the **License Agreement** dialog box, click the **I accept the terms of the license agreement** button. To print the license agreement, click **Print**. Click **Next** to proceed.
4. At the **Ready to Install the Program** dialog box, click **Install**.
The License Server and License Server Utility will be installed using the settings you specified in the previous steps.
5. At the **Install Wizard Completed** dialog box, click **Finish**.

The License Server upgrade is installed.

Progress and Resolution of Outstanding Issues

Issue Number	Description and Resolution
MIPRO-35627	The service, MapInfo License Server, is unable to start automatically on restarting the machine. Resolution: Fixed.